

#### 4010 command & responses:

Command	Responses
@MS,001,{seq name},{point}\r\n ^x	
@TS,001,{seq name},{point}\r\n ^x	
@S,001\r\n ^x	
@P,001\r\n ^x	
@GS,001,D\r\n	\r{dil mfc ctl}, {dil mfc mon}, {o3 mfc ctl},{o3 mfc mon}, {src mfc #}, {src mfc ctl},{src mfc mon},{sys temp},DDDDDDDDDD, SSSSSS\r
@GS,001,G\r\n	src mfc ctl = 0: \r{total flow mon}, {num gases},\r src mfc ctl != 0: \r{total flow mon}, {num gases},\r{prim gas name}, {prim gas conc},\r

#### CommandMode :

Value	Mode
0	get dilution
1	get Oppb gas
2	get gas
3	MS/TS/Stop/Purge

#### CommandStatus :

Value	Status
-1	error
0	idle
1	success